


Quick guide to ARCHIVE a project on DIGSI 4


Please refer to the following steps to archive a project on DIGSI 4

1. Before archiving the project for the first time, carry out the following basic settings
If it is not your first time archiving projects, skip to step 4

Options -> Customize




2. **Select an archiving program** from the 'Preferred Archiving Program' list
Check if the desired program is installed. If necessary install it.
(All the supported programs are offered for selection, irrespective of the programs installed on your machine.)



3. Configuring Archive Program

Configure all archive programs used by you consecutively.


Specify the path in which the archive program is installed in the the Program Path box. The file name without drive is and directory specifications is preset. This information is sufficient provided that the archive program lies within a directory specified in the search path. If this is not the case, the absolute program path has to be entered by clicking on **Browse**.





4. Archiving the Project


Close the project to be archived.

Go to **File -> Archive**.



- Select the project to be archived under User projects.





Please feel free to contact us if you have any questions.